



ForeScout

Core Extensions Module: Syslog Plugin

Configuration Guide

Version 3.6.1



Contact Information

Forescout Technologies, Inc.

190 West Tasman Drive

San Jose, CA 95134 USA

<https://www.Forescout.com/support/>

Toll-Free (US): 1.866.377.8771

Tel (Intl): 1.408.213.3191

Support: 1.708.237.6591

About the Documentation

- Refer to the Technical Documentation page on the Forescout website for additional documentation: <https://www.Forescout.com/company/technical-documentation/>
- Have feedback or questions? Write to us at documentation@forescout.com

Legal Notice

© 2020 Forescout Technologies, Inc. All rights reserved. Forescout Technologies, Inc. is a Delaware corporation. A list of our trademarks and patents can be found at <https://www.Forescout.com/company/legal/intellectual-property-patents-trademarks>. Other brands, products, or service names may be trademarks or service marks of their respective owners.

2020-06-16 16:36

Table of Contents

About the Syslog Plugin	4
Multiple Destination Syslog Server Support.....	4
Receiving Event Messages	4
Sending Syslog Messages.....	5
Sending Forescout Event Messages.....	5
Using Actions to Send Endpoint Messages	5
Syslog Requirements.....	6
Configuration	6
Select an Appliance to Configure	6
Send Events To.....	7
Facility Values.....	8
Severity Values.....	9
Syslog Triggers	10
Including Header Information in All Message.....	10
Selecting Syslog Message Triggers	11
NAC Events	12
Threat Protection.....	12
System Logs and Events	13
User Operations	13
Operating System Messages	13
Default Action Configuration	14
Receive From.....	14
Certificate Management	16
Verify That the Plugin Is Running	16
Testing the Plugin Configuration.....	16
Downloading and Configuring NTSyslog.....	17
Create Custom Syslog Policies.....	20
Send Message to Syslog Action	21
Working with Property Tags.....	22
Core Extensions Module Information	23
Additional Forescout Documentation.....	23
Documentation Downloads	23
Documentation Portal	24
Forescout Help Tools.....	24

About the Syslog Plugin


The Syslog Plugin is a component of the Forescout® Core Extensions Module. See [Core Extensions Module Information](#) for details about the module.

The Syslog Plugin lets you send, receive and format messages to and from external Syslog servers. You can configure each Forescout device to:

- Send all event messages to one or more Syslog servers.
- Receive messages from up to three manually configured Syslog servers.

Multiple Destination Syslog Server Support

The following diagram provides an example of communication from Forescout devices to Syslog servers.



Receiving Event Messages

Receiving event messages from external Syslog servers allows the Forescout platform to gain visibility into events that cannot be obtained from analyzing traffic either because:

- Traffic is not visible to any of the deployed Forescout Appliances.
- Traffic is encrypted.

Login events are recorded on Windows Domain Controllers. When these events are received by the Syslog Plugin, the Forescout platform knows immediately if an endpoint has been authenticated to the Domain Controller and which User and Domain Name were used for authentication. The Forescout platform parses the received messages, and updates the relevant host properties. This information is displayed in the Profile tab of the Console Home view.

To receive messages from external Syslog servers, configure the [Receive From](#) plugin configuration tab.

Sending Syslog Messages

Sending valuable information from the Forescout platform to one or more external Syslog servers allows the information to be used for event aggregation, auditing, and further processing. For a description of the contents of the different Syslog message types generated by the Forescout platform, refer to Forescout Technical Notes: *Syslog Messages Sent by Forescout*. See [Additional Forescout Documentation](#) for information about accessing this document.

There are two types of messages that you can send to Syslog:

- [Sending Forescout Event Messages](#)
- [Using Actions to Send Endpoint Messages](#)

Sending Forescout Event Messages

You can configure the plugin to send ongoing messages about Forescout system events from one Forescout device to one or more Syslog servers using the configuration settings in the Syslog Plugin. See [Configuration](#).

Each Forescout device receives unique event information from the network, and will only send events to Syslog that occurred within the network segment of the Forescout device. This is important to consider when configuring which Forescout devices send messages to Syslog servers.

The Forescout platform can be configured to send a message to the configured Syslog servers each time a new event of the following type occurs:

- [NAC Events](#)
- [Threat Protection](#)
- [System Logs and Events](#)
- [User Operations](#)
- [Operating System Messages](#)

Using Actions to Send Endpoint Messages

You can send customized messages to Syslog for specific endpoints using the Forescout eyeSight *Send Message to Syslog* action, either manually or in Forescout platform policies. Use the action to send messages based on policy results or at customizable intervals. See [Send Message to Syslog Action](#).

Syslog Requirements

This section provides the requirements for configuring and running the Forescout Syslog Plugin.

Forescout Requirements

The following Forescout platform and component versions must be running in your Enterprise Manager and your Appliances:

- Forescout interim release 8.2.1
- Core Extensions Module 1.2.1 with the Syslog Plugin

Configuration


This section describes how to configure the Syslog Plugin.

Select an Appliance to Configure


This section describes how to configure the plugin to ensure that the Forescout device can properly communicate with Syslog servers.

To configure the Syslog Plugin:

1. In the Modules pane, select **Core Extensions** > **Syslog** and then select **Appliances**. The *Syslog - Appliances Installed* dialog box opens.



2. Select any Appliance or the Enterprise Manager and select **Configure**. You cannot configure multiple Forescout devices simultaneously. The *Configuration* dialog box opens.



3. See the following sections to complete the information in each tab:


- [Send Events To](#)
- [Syslog Triggers](#)
- [Default Action Configuration](#)
- [Receive From](#)

4. When the configuration is complete, select **OK**.

Send Events To

The *Send Events To* tab lists the Syslog servers to which the Forescout device will send messages regarding the event types selected in the [Syslog Triggers](#) tab. For each Syslog server, define:

- The details that the Forescout platform needs to communicate with the server
- The *Facility*, *Severity*, and *Message Identity* values to be included in all event messages



To configure the Forescout platform to send event messages to Syslog servers:

- In the *Send Events To* tab, do one of the following:
 - To define a Syslog server not in the table, select **Add**.
 - To modify the definition of an existing server, select it in the table and select **Edit**.
- Specify the following information for the server:

Field	Description
Server Address	Syslog server IP address or fully qualified domain name (FQDN).
Server Port	Syslog server port.
Server Protocol	Syslog messaging can use TCP or UDP. Select the protocol to be used for communicating with this Syslog server.
Use TLS	For some server types, you can to instruct the Forescout platform to use TLS to encrypt communication with the Syslog server.
Soft-fail OCSP Requests	If the Forescout platform could not receive a response from the OCSP Responder, the certificate is considered valid. By default, hard-fail is applied. In order to use this option, you must <i>also</i> enable the Use TLS option.
Message Identity	Free-text field for identifying the Syslog message.
Facility	Syslog message facility that is transmitted as part of the message Priority field. For valid values, see Facility Values .
Severity	Syslog message severity that is transmitted as part of the message Priority field. For valid values, see Severity Values .

- Select **OK**. The updated server definition appears in the table.
- (Optional) To delete a server, select it in the table and select **Remove**.

For the certificates required when using *Send Events To Syslog servers*, see [Certificate Management](#).

Facility Values

The Syslog message facility must be one of the values in the following table:

Facility Value	IETF Facility Description
kern	kernel messages
kernel	
user	user-level messages

Facility Value	IETF Facility Description
mail	mail system
daemon	system daemons
system	
auth	security/authorization messages
syslog	messages generated internally by syslogd
internal	
lpr	line printer subsystem
printer	
news	network news subsystem
uucp	UUCP subsystem
cron	clock daemon
clock	
authpriv	security/authorization messages
security2	
ftp	FTP daemon
FTP	
NTP	NTP subsystem
audit	log audit
alert	log alert
clock2	clock daemon
local0	local use 0
local1	local use 1
local2	local use 2
local3	local use 3
local4	local use 4
local5	local use 5
local6	local use 6
local7	local use 7

If the facility value is not valid, it is set to **local5**.

Severity Values

The Syslog message severity must be one of the values in the following table:

Severity Value	IETF Severity Description
emergency	system is unusable
emerg	

Severity Value	IETF Severity Description
alert	action must be taken immediately
critical	critical conditions
crit	
error	error conditions
err	
warning	warning conditions
notice	normal but significant condition
informational	informational messages
info	
debug	debug-level messages


If the severity value is not valid, it is set to **error**.

Syslog Triggers

Configure the settings in the *Syslog Triggers* tab.

Including Header Information in All Message

The *Syslog Triggers* tab contains a setting that applies to all Syslog messages sent from the Forescout device.



Select **Include timestamp and CounterACT device identifier in all messages** to include in all Syslog messages:


- A timestamp
 - The device name or IP address of the Forescout device sending the message
- 📄 *If Device Name is selected but cannot be resolved, the Forescout device IP address is included in its place.*

These fields comply with the RFC 3164 specification for BSD Syslog.

Selecting Syslog Message Triggers

Syslog messages can be generated by Forescout platform policies when endpoints meet conditional criteria.


To enable Syslog messages to be generated by events and not only by policies, the **Include only messages generated by the "Send Message to Syslog" action** checkbox must *not* be selected.



If the **Include only messages generated by the "Send Message to Syslog" action** checkbox is not selected, you can select options in the tab to define which event types trigger Syslog messages.

You can select event triggers from the following categories:

- [NAC Events](#)
- [Threat Protection](#)
- [System Logs and Events](#)
- [User Operations](#)
- [Operating System Messages](#)



NAC Events

These event messages contain information on all policy event logs.

Message	Description
NAC policy logs	Endpoint policy events. The log displays information about endpoints as they are detected and is continuously updated as the policy is evaluated for the endpoint.
NAC policy match/unmatch events	Policy evaluation change events.

Threat Protection

These event messages contain information on intrusion-related activity, including bite events, scan events, lockdown events and manual events. These messages can be triggered when the Syslog Plugin runs on an Appliance but not when it runs on an Enterprise Manager.

Message	Description
Bite events	Indicates that an endpoint has tried to gain access to your network using a system mark.

Message	Description
Scan events	Indicates that an endpoint has performed a specific probe a defined number of times within a defined time period. By default, when an endpoint initiates three probes within one day, the Forescout platform considers this activity a scan.
Lockdown events	Indicates that a malicious event has been detected by another Appliance.
Block events	Indicates that the Forescout platform has blocked packets from the source from going through to the specified destination (host + service).
Email worm events	Indicates that the Forescout platform has identified email worm anomalies sent over email.

System Logs and Events

These event messages contain information about the Forescout platform system events.

Message	Description
System uptime events	Indicates the amount of time the Forescout service has been running.
System log events	Indicates certain Forescout platform activities detected by the system. For example, successful and failed user login operations. (Messages sent to the Event Viewer)
System status messages	Indicates memory, swap and CPU usage statistics.
Packet Engine status messages	Indicates the status of the Forescout service that monitors and injects SPAN port traffic. If it is down, many Forescout features will not work.

User Operations

These event messages are generated when a user operation takes place, and they are included in the Audit Trail.

Message	Description
User operations	Indicates that the user made a configuration change such as updating policies, stopping or starting the device, or updating user passwords.


Operating System Messages

These event messages are generated by the operating system.

Message	Description
Operating system messages	Indicates an event of relevance at the level of the operating system. This is useful, for example, if you want to monitor the health of an Appliance or Enterprise Manager by sending the events to a SIEM.

Default Action Configuration

The *Default Action Configuration* tab allows you to define default values for the *Send Message to Syslog* action parameters. These default values are applied to parameters that are not defined in policies. See [Send Message to Syslog Action](#) for details.



The screenshot shows a configuration window titled "Syslog@Enterprise Manager Plugin Configuration". It has four tabs: "Send Events To", "Syslog Triggers", "Default Action Configuration" (which is selected), and "Receive From". The "Default Action Configuration" tab contains the following fields:

- Server Address: [Empty text box]
- Server Port: 514 (with up/down arrows)
- Server Protocol: UDP (dropdown menu)
- Message Identity: CounterACT
- Facility: local4
- Severity: info

Specify the following values:

Field	Description
Server Address	Syslog server IP address or fully qualified domain name.
Server Port	Syslog server port.
Server Protocol	Syslog messaging can use TCP or UDP. Select the protocol to be used for communicating with this server.
Message Identity	Free-text field for identifying the Syslog message.
Facility	Syslog message facility that is transmitted as part of the message Priority field. For valid values, see Facility Values .
Severity	Syslog message severity that is transmitted as part of the message Priority field. For valid values, see Severity Values .

Receive From

The *Receive From* tab allows you to define:

- Up to three Syslog agents from which the plugin may receive Syslog messages.
- Which ports the plugin will use to listen for messages being sent from the defined Syslog agents.

For each Syslog agent, define its *Source Type* and its *IP Address*. Currently, the only source type supported is NTSyslog security log. You must download and configure NTSyslog on an organizational domain controller to work with the *Receive From* feature. See [Downloading and Configuring NTSyslog](#).

Received messages are not stored by the Forescout platform.

To configure Syslog sources:

1. Per Syslog source, define the following:
 - a. In the *Source Type* field, select **NTSyslog security log** from the dropdown menu.
 - b. In the *IP Address* field, enter the IP address or fully qualified domain name (FQDN) of the domain controller.
 2. In the *Ports for Incoming Syslog Messages* section, define either one or both of the following:
 - a. In the *UDP Port* field, enter the UDP port that is used for listening for incoming Syslog messages. By default, *UDP Port* is set to 514.
 - b. In the *TCP Port* field, enter the TCP port that is used for listening for incoming Syslog messages. By default, *TCP Port* is set to 0 and is not used.
- A port is not used for listening for incoming Syslog messages, when its value is set to 0.*

3. Enable the **Use TLS** option to instruct the Forescout platform to use TLS to encrypt communication with the Syslog sources. By default, this option is disabled.

For the certificates required when using *Receive From* Syslog servers, see [Certificate Management](#).

Certificate Management

When the Syslog Plugin is configured to use TLS to establish secure communication connections for the following use cases, you must define certificates:

- The plugin is configured to *Send Events To* Syslog servers, define each Syslog server's trusted certificate chain
- The plugin is configured to *Receive From* Syslog server sources, define the system certificate for the Syslog Plugin to present to each sender source
- For the plugin to apply the *Send Message to Syslog* action, define the targeted Syslog server's trusted certificate chain

Use the Console certificate interface to:

- Define and provision the system certificate for plugin presentation to each external, sender source for validation of the certificate. In the Console, access **Options > Certificates > System Certificates**.
- Configure the certificate authority (CA) trust chain of each external server for plugin authentication of these servers. In the Console, access **Options > Certificates > Trusted Certificates**.

In the *Forescout Administration Guide*, refer to the appendix titled *Configuring the Certificate Interface* for information about working with the Console certificate interface. See [Additional Forescout Documentation](#) for information on how to access this guide.

Verify That the Plugin Is Running

After configuring the plugin, verify that it is running.

To verify:



1. Select **Tools>Options** and then select **Modules**.
2. Navigate to the plugin and select **Start** if the plugin is not running.

Testing the Plugin Configuration

Use the test option to verify that the Forescout platform can communicate with the Syslog servers defined in the plugin configuration *Send Events To* tab.

To test the plugin configuration:

1. In the *Modules* pane, select **Core Extensions** > **Syslog** and then select **Test**. A confirmation message appears identifying Forescout devices on which the test will be performed.
2. Select **Yes** to begin the plugin test. The Plugin Test dialog box displays information about each Forescout device tested, as well as a number of test messages.



3. Verify that the Syslog servers received the messages displayed in the dialog box.


Downloading and Configuring NTSyslog

NTSyslog is a tool that sends Active Directory security logs to the Forescout platform if the Syslog Plugin is configured to receive messages. See [Receive From](#) to configure the plugin to receive messages.

To download and configure NTSyslog:

1. Install NTSyslog to your organizational Domain Controller. Use <http://sourceforge.net/projects/ntsyslog/> or download from another location.


2. Open the NTSyslog Service Control Manager.




3. Select Syslog Daemons.



- In the *Primary Syslog Daemon* field, enter the IP address of the Forescout device to which traffic must be sent, and select **OK**.




- In the NTSyslog Service Control Manager *EventLog* dropdown menu, select **Security**, and then select **EventLog**. Ensure that all events are selected.



- Select **OK**.

7. Select **Start Service**, and verify that the *Service is running* message appears in the *NTSyslog Service Manager* dialog box.



Create Custom Syslog Policies

Policy tools provide you with an extensive range of options for detecting and handling endpoints. You can use a policy to instruct the Forescout platform to apply the [Send Message to Syslog Action](#) to endpoints that match conditions based on reported endpoint properties.


To create a custom policy:

1. Log in to the Forescout Console.
2. On the Console toolbar, select the **Policy** tab. The *Policy Manager* opens.
3. Select **Add** to create a policy.

 For more information about working with policies, select **Help** from the policy wizard.

Send Message to Syslog Action

Use the *Send Message to Syslog* action, grouped in the *Audit* category of actions, to send a Syslog message to an external Syslog server.



Specify the following configuration fields for the Syslog message, or accept the default values that were defined during plugin configuration. See [Default Action Configuration](#).


Field	Description
Message to Syslog	The text message that is sent to the Syslog server. You can use property tags to include endpoint data values. See Working with Property Tags .
Message Identity	Free-text field for identifying the Syslog message.
Syslog Server Address	Syslog server IP address or fully qualified domain name.
Syslog Server Port	Syslog UDP port number.
Syslog Server Protocol	Syslog messaging can use TCP or UDP. Select the protocol used to communicate with this server.
Syslog Facility	Syslog message facility that is transmitted as part of the message Priority field. For valid values, see Facility Values .
Syslog Severity	Syslog message severity that is transmitted as part of the message Priority field. For valid values, see Severity Values .

Field	Description
Use TLS	For some server types, you can to instruct the Forescout platform to use TLS to encrypt communication with the Syslog server.
Soft-fail OCSP Requests	If the Forescout platform could not receive a response from the OCSP Responder, the certificate is considered valid. By default, hard-fail is applied. In order to use this option, you must <i>also</i> enable the Use TLS option.
Tags	To add property tags, see Working with Property Tags

For the certificates required in order for the plugin to apply the *Send Message to Syslog* action, see [Certificate Management](#).

Working with Property Tags

You can add current values of host properties to the message. Select **Add Tags** to insert a placeholder that is populated with the actual value of the host property when the message is generated.



Core Extensions Module Information

The Syslog Plugin is installed with the Forescout Core Extensions Module.

The Forescout Core Extensions Module provides an extensive range of capabilities that enhance the core Forescout solution. These capabilities enhance detection, classification, reporting, troubleshooting, and more. The following components are installed with the Core Extensions Module:

Advanced Tools Plugin	Device Data Publisher	IoT Posture Assessment Engine
CEF Plugin	DNS Client Plugin	
Cloud Uploader	DNS Enforce Plugin	NBT Scanner Plugin
DHCP Classifier Plugin	DNS Query Extension Plugin	Packet Engine
Dashboards Plugin	External Classifier Plugin	Reports Plugin
Data Publisher	Flow Analyzer Plugin	Syslog Plugin
Data Receiver	Flow Collector	Technical Support Plugin
Device Classification Engine	IOC Scanner Plugin	Web Client Plugin

The Core Extensions Module is a Forescout Base Module. Base Modules are delivered with each Forescout release. Upgrading the Forescout version or performing a clean installation installs this module automatically.

Additional Forescout Documentation

For information about other Forescout features and modules, refer to the following resources:

- [Documentation Downloads](#)
- [Documentation Portal](#)
- [Forescout Help Tools](#)

Documentation Downloads

Documentation downloads can be accessed from the [Technical Documentation Page](#), and one of two Forescout portals, depending on which licensing mode your deployment is using.

- **Per-Appliance Licensing Mode** – [Product Updates Portal](#)
- **Flexx Licensing Mode** – [Customer Support Portal](#)

 *Software downloads are also available from these portals.*

To identify your licensing mode:

- From the Console, select **Help > About Forescout**.

Technical Documentation Page

The Forescout Technical Documentation page provides a link to the searchable, web-based [Documentation Portal](#), as well as links to a wide range of Forescout technical documentation in PDF format.

To access the Technical Documentation page:

- Go to <https://www.Forescout.com/company/technical-documentation/>

Product Updates Portal

The Product Updates Portal provides product and documentation downloads for Forescout platform releases, Base Modules, Content Modules, and eyeExtend products. The portal also provides additional documentation.

To access the Product Updates Portal:

- Go to <https://updates.forescout.com/support/index.php?url=counteract> and select the version you want to discover.

Customer Support Portal

The Downloads page on the Forescout Customer Support Portal provides product and documentation downloads for Forescout platform releases, Base Modules, Content Modules, and eyeExtend products. Software and related documentation only appear on the Downloads page if you have a license entitlement for the software.

To access documentation on the Customer Support Portal:

- Go to <https://Forescout.force.com/support/> and select **Downloads**.

Documentation Portal

The Forescout Documentation Portal is a searchable, web-based library containing information about Forescout tools, features, functionality, and integrations.

To access the Documentation Portal:

- Go to https://updates.forescout.com/support/files/counteract/docs_portal/

Forescout Help Tools

You can access individual documents, as well as the [Documentation Portal](#), directly from the Console.

Console Help Buttons

- Use context sensitive *Help* buttons to quickly access information about the tasks and topics you are working with in the Console.

Forescout Administration Guide

- Select **Administration Guide** from the **Help** menu.

Plugin Help Files

- After the plugin is installed, select **Tools > Options > Modules**, select the plugin, and then select **Help**.

Content Module, eyeSegment Module, and eyeExtend Product Help Files

- After the component is installed, select **Tools > Options > Modules**, select the component, and then select **Help**.

Documentation Portal

- Select **Documentation Portal** from the **Help** menu.
-