



# Fore Scout

## Device Profile Library

### Configuration Guide

**Version 20.1.11**



## Contact Information

Forescout Technologies, Inc.

190 West Tasman Drive

San Jose, CA 95134 USA

<https://www.Forescout.com/support/>

Toll-Free (US): 1.866.377.8771

Tel (Intl): 1.408.213.3191

Support: 1.708.237.6591

## About the Documentation

- Refer to the Technical Documentation page on the Forescout website for additional documentation: <https://www.Forescout.com/company/technical-documentation/>
- Have feedback or questions? Write to us at [documentation@forescout.com](mailto:documentation@forescout.com)

## Legal Notice

© 2020 Forescout Technologies, Inc. All rights reserved. Forescout Technologies, Inc. is a Delaware corporation. A list of our trademarks and patents can be found at <https://www.Forescout.com/company/legal/intellectual-property-patents-trademarks>. Other brands, products, or service names may be trademarks or service marks of their respective owners.

2020-11-17 22:36

## Table of Contents

<b>About the Device Profile Library</b> .....	<b>4</b>
<b>How It Works</b> .....	<b>4</b>
<b>Forescout Requirements</b> .....	<b>5</b>
<b>Install the Module</b> .....	<b>6</b>
<b>Configure the Device Profile Library</b> .....	<b>7</b>
Check for Policy Issues .....	7
<b>Additional Forescout Documentation</b> .....	<b>8</b>
Documentation Downloads .....	8
Documentation Portal .....	9
Forescout Help Tools.....	9
<b>Appendix A: Ports and Protocols</b> .....	<b>10</b>

## About the Device Profile Library

The Forescout Device Profile Library is a Content Module that delivers a library of pre-defined device classification *profiles*, each composed of properties and corresponding values that match a specific device type. Each profile maps to a combination of values for function, operating system, and/or vendor and model. For example, the profile defined for *Apple iPad* considers the set of properties which includes the hostname of the device revealed by DHCP traffic, the HTTP banner, the NIC vendor and Nmap scan results. The Forescout Device Classification Engine (a component of the Forescout Core Extensions Module) classifies any endpoint with property values matching those specified in the *Apple iPad* classification profile as:

- *Function*: Information Technology > Mobile > Tablet
- *Operating System*: iOS
- *Vendor and Model*: Apple > Apple iDevice > Apple iPad

The classification values form a tree-structured taxonomy that ultimately describes what the endpoint is. The Device Classification Engine uses these classification profiles to classify devices that are detected in your network.

The classification profile content is updated periodically to improve the quality and breadth of profiles so that more devices types can be classified even more precisely. It is recommended to install the latest version of the Device Profile Library to take advantage of the most current classifications.

## How It Works

The Device Classification Engine uses information provided by the Device Profile Library to provide the best possible classification for the device based on the properties available to Forescout eyeSight. Refer to the *Forescout Core Extensions Module: Device Classification Engine Configuration Guide*. See [Additional Forescout Documentation](#) for information on how to access the guide.

Function	Lists	No. of Hosts	Last Update	Last Host	Full Classification Path
Computer		214	6/12/19 2:19:14 PM		Information Technology > Comput...
Information Technology		3	6/12/19 5:37:53 AM		Information Technology
Mobile		1	6/11/19 10:01:47 PM		Information Technology > Mobile
Networking		5	6/12/19 1:14:25 PM		Information Technology > Networ...
Printer		1	6/12/19 5:25:51 AM		Information Technology > Access...
Router or Switch		1	6/12/19 8:29:39 AM		Information Technology > Networ...
Server		97	6/12/19 2:15:49 PM		Information Technology > Comput...
Unknown		27	6/12/19 2:16:47 PM		Unknown

Each detected endpoint may be classified according to three different metrics:

- Function
- Operating System
- Vendor and Model

The taxonomy of each classification metric is based on a tree structure. Each level in the tree is more specific than the level above it. Endpoints are classified to the most specific value that eyeSight can resolve.


## Forescout Requirements

The module requires the following:

- Forescout version 8.1, 8.2.0, or 8.2.1

For optimal endpoint classification, it is recommended to install the **highest available versions** of the following Forescout components, and ensure they are running:

- Core Extensions Module, including the following plugins:
  - DHCP Classifier Plugin
  - Device Classification Engine
- Windows Applications Content Module
- Endpoint Module, including the following plugins:
  - HPS Inspection Engine
  - Linux Plugin, if there are Linux endpoints in your environment
  - OS X Plugin, if there are macOS/OS X endpoints in your environment
- NIC Vendor DB Content Module
- Network Module including the Switch Plugin
- Hybrid Cloud Module, including either:
  - Amazon Web Services (AWS) Plugin
  - Microsoft Azure Plugin
- Operational Technology Module

 *If you have the Medigate Platform deployed in your environment, it is recommended to ensure that the Forescout Medigate Module is installed and running.*

# Install the Module

The Device Profile Library is included in the installation of Forescout eyeSight. It is recommended to install the latest available version of the module to take advantage of the most current classifications.


After a new version of the Device Profile Library is installed, it is recommended to run a policy that resolves classification properties. Due to classification profile changes in the new library version, some device classifications may change. Before these changes are applied to the endpoints, you can review all the pending changes and decide if you want to apply them, modify existing policies and then apply them, or cancel the changes and roll back to a previous Device Profile Library version. For details, refer to the *Forescout Core Extensions Module: Device Classification Engine Configuration Guide*. See [Additional Forescout Documentation](#) for information on how to access the guide.


## To install the module:

1. Navigate to one of the following Forescout download portals, depending on the licensing mode your deployment is using:
  - [Product Updates Portal](#) - **Per-Appliance Licensing Mode**
  - [Customer Portal, Downloads Page](#) - **Flexx Licensing Mode**

To identify your licensing mode, select **Help > About ForeScout** from the Console.

2. Download the module **.fpi** file.
3. Save the file to the machine where the Console is installed.
4. Log into the Console and select **Options** from the **Tools** menu.
5. Select **Modules**. The Modules pane opens.
6. Select **Install**. The Open dialog box opens.
7. Browse to and select the saved module **.fpi** file.
8. Select **Install**. The Installation screen opens.
9. Select **I agree to the License Agreement** to confirm that you have read and agree to the terms of the License Agreement and select **Install**. The installation cannot proceed unless you agree to the license agreement.

 *The installation begins immediately after selecting Install and cannot be interrupted or canceled.*

 *In modules that contain more than one component, the installation proceeds automatically one component at a time.*

10. When the installation completes, select **Close** to close the window. The installed module is displayed in the Modules pane.

 *Some components are not automatically started following installation.*

# Configure the Device Profile Library

Endpoints are classified only after the *Function*, *Operating System*, or *Vendor and Model* classification properties are used in a policy. It is recommended to use the *Primary Classification* policy template to fully leverage the Device Classification Engine technology.

## Check for Policy Issues

Each release of the Device Profile Library brings new content. Use this command line utility to parse policies and check against new content. This way you can review and adjust your policies if needed.

This check can be run from the Forescout appliance command line terminal:

```
fstool profiles do_policy_scan
```

Example of output if errors are found in the policies:

```
POLICY ERRORS FOUND:
```

```
Policy: FS Lab Devices
```

```
  Main Rule
```

```
    Obsolete values for property 'Vendor and Model':
```

```
      GE/GE Healthcare/GE Signa MRI Scanner/GE Signa Excite Profile
```

```
    Obsolete values for action 'Set OS Classification':
```

```
      ProCurve R.11.25
```

```
  Sub-Rule: FS Lab Siemens devices
```

```
    Obsolete values for property 'Vendor and Model':
```

```
      Siemens/Siemens SIPLUS PCS 7 CPU410-5H
```

```
  Sub-Rule: FS Lab Checkpoint devices
```

```
    Obsolete values for property 'Operating System':
```

```
      Check Point IPSO/Check Point R75
```

```
  Sub-Rule: Set FS Lab device
```

```
    Obsolete values for action 'Set Vendor and Model Classification':
```

```
      IBM iConnect Access Version 7.0
```

```
Policy: Primary Classification
```

```
  Sub-Rule: Macintosh
```

```
    Obsolete values for property 'Operating System':
```

```
      Macintosh
```

## Additional Forescout Documentation

For information about other Forescout features and modules, refer to the following resources:

- [Documentation Downloads](#)
- [Documentation Portal](#)
- [Forescout Help Tools](#)

### Documentation Downloads

Documentation downloads can be accessed from the [Technical Documentation Page](#), and from one of two Forescout portals, depending on which licensing mode your deployment is using.

- **Per-Appliance Licensing Mode** – [Product Updates Portal](#)
- **Flexx Licensing Mode** – [Customer Support Portal](#)

 Software downloads are also available from these portals.

#### To identify your licensing mode:

- From the Console, select **Help > About Forescout**.

### Technical Documentation Page

The Forescout Technical Documentation page provides a link to the searchable, web-based [Documentation Portal](#), as well as links to a wide range of Forescout technical documentation in PDF format.

#### To access the Technical Documentation page:

- Go to <https://www.Forescout.com/company/technical-documentation/>

### Product Updates Portal

The Product Updates Portal provides product and documentation downloads for Forescout platform releases, Base Modules, Content Modules, and eyeExtend Modules. The portal also provides additional documentation.

#### To access the Product Updates Portal:

- Go to <https://updates.forescout.com/support/index.php?url=counteract> and select the version you want to discover.

### Customer Support Portal

The Downloads page on the Forescout Customer Support Portal provides product and documentation downloads for Forescout platform releases, Base Modules, Content Modules, and eyeExtend Modules. Software and related documentation only appear on the Downloads page if you have a license entitlement for the software.



**To access documentation on the Customer Support Portal:**

- Go to <https://Forescout.force.com/support/> and select **Downloads**.

## Documentation Portal

The Forescout Documentation Portal is a searchable, web-based library containing information about Forescout tools, features, functionality, and integrations.

**To access the Documentation Portal:**

- Go to [https://updates.forescout.com/support/files/counteract/docs\\_portal/](https://updates.forescout.com/support/files/counteract/docs_portal/)

## Forescout Help Tools

You can access individual documents, as well as the [Documentation Portal](#), directly from the Forescout Console.

***Console Help Buttons***

- Use context sensitive *Help* buttons to quickly access information about the tasks and topics you are working with in the Console.

***Forescout Administration Guide***

- Select **Administration Guide** from the **Help** menu.

***Plugin Help Files***

- After the plugin is installed, select **Tools > Options > Modules**, select the plugin, and then select **Help**.

***Content Module, eyeSegment Module, and eyeExtend Module Help Files***

- After the component is installed, select **Tools > Options > Modules**, select the component, and then select **Help**.

***Documentation Portal***

- Select **Documentation Portal** from the **Help** menu.

## Appendix A: Ports and Protocols

The following table lists all the destination ports that may be queried on endpoints during the classification process.

Port	Protocol	Device
21	TCP	Network Attached Storage Device
22	TCP	Network Attached Storage Device
80	TCP	Temperature Monitor
102	TCP	PLC Device
104	TCP	DICOM Server
111	TCP	Printer
161	UDP	Networking Device
161	UDP	Printer
443	TCP	Network Attached Storage Device
500	UDP	Medication Dispensing System
515	TCP	Printer
554	TCP	IP Camera
1720	TCP	VoIP Device
1732	UDP	Patient Monitor
1801	TCP	Medication Dispensing System
1950	TCP	Patient Monitor
2000	TCP	Patient Monitor
2000	TCP	Medical Cart
2050	TCP	Patient Monitor
2100	TCP	Patient Monitor
2150	TCP	Patient Monitor
2222	UDP	PLC Device
5247	UDP	Networking Device
5684	UDP	IKEA Gateway
8080	TCP	Network Attached Storage Device
9007	TCP	Printer
9100	TCP	Printer
24000	TCP	Philips Intellivue Device
24001	TCP	Philips Intellivue Device
24002	TCP	Philips Intellivue Device
24003	TCP	Philips Intellivue Device
24004	TCP	Philips Intellivue Device

Port	Protocol	Device
24005	TCP	Philips Intellivue Device
44818	TCP	PLC Device
51243	TCP	Infusion Pump
53213	UDP	Printer
62078	TCP	Mobile Device