

August 2020

Version Information

Forescout eyeExtend for Tenable® Vulnerability Management (VM) version 3.0.2.
This section describes requirements for this version.

Forescout Requirements

- Forescout version 8.1.2.
- A module license for Forescout eyeExtend for Tenable VM. See [Forescout eyeExtend \(Extended Module\) Licensing Requirements](#) for details.


Forescout eyeExtend (Extended Module) Licensing Requirements

This Forescout eyeExtend module requires a valid license. Licensing requirements differ based on which licensing mode your deployment is operating in:

- [Per-Appliance Licensing Mode](#)
- [Flexx Licensing Mode](#)

To identify your licensing mode:

- From the Console, select **Help > About Forescout.**



Per-Appliance Licensing Mode

When installing the module, you are provided with a 90-day demo license.

If you would like to continue exploring the module before purchasing a permanent license, you can request a demo license extension. Consult with your Forescout representative before requesting the extension. You will receive email notification and alerts at the Console before the demo period expires.

To continue working with the module after the demo period expires, you must purchase a permanent module license.

Demo license extension requests and permanent license requests are made from the Console.

This module may have been previously packaged as a component of an Integration Module which contained additional modules. If you already installed this module as a component of an Integration Module, you can continue to use it as such. Refer to the section about module packaging in the Forescout Administration Guide for more information.

Requesting a License


When requesting a demo license extension or permanent license, you are asked to provide the device *capacity* requirements. This is the number of devices that you want this license to handle. You must define at least the number of devices currently detected by the Forescout platform. You can request a license that handles more to ensure that you are licensed for support on additional devices as your deployment grows.

Enter this number in the **Devices** pane of the Module License Request wizard, in the Console Modules pane.




To view the number of currently detected devices:

1. Select the **Home** tab.
2. In the Views pane, select the **All Hosts** folder. The number in parentheses displayed next to the **All Hosts** folder is the number of devices currently detected.




Flexx Licensing Mode

When you set up your Forescout deployment, you must activate a license file containing valid licenses for each feature you want to work with in your deployment, including eyeExtend modules. After the initial license file has been activated, you can update the file to add additional eyeExtend licenses or change endpoint capacity for existing eyeExtend modules. For more information on obtaining eyeExtend licenses, contact your Forescout sales representative.

 *No demo license is automatically installed during system installation.*

License entitlements are managed in the [Forescout Customer Portal](#). After an entitlement has been allocated to a deployment, you can activate or update the relevant licenses for the deployment in the Console.

Each eyeExtend license has an associated capacity, indicating the number of endpoints the license can handle. The capacity of each eyeExtend license varies by module but does not exceed the capacity of the Forescout eyeSight license.

 *Integration Modules, which package together groups of related licensed modules, are not supported when operating in Flexx Licensing Mode. Only eyeExtend modules, packaging individual licensed modules are supported. The eyeExtend Connect Module is an eyeExtend module even though it packages more than one module.*

More License Information

For more information on eyeExtend (Extended Module) licenses:

- **Per-Appliance Licensing.** Refer to the *Forescout Administration Guide*.
- **Flexx Licensing.** Refer to the *Flexx Licensing How-to Guide*.

You can also contact your Forescout sales representative for more information.

Supported Vendor Requirements

- Forescout eyeExtend for Tenable VM supports the following Tenable Network Security product for communication: Tenable.sc versions 5.6.x, 5.9.x, 5.10.x, 5.11.x, and 5.12.0.
- For information about the vendor models (hardware/software) and versions (product/OS) that are validated for integration with this Forescout component, refer to the [Forescout Compatibility Matrix](#).

Verify that your Tenable servers and their connected CounterACT devices regularly synchronize their clocks with the same NTP server.

About This Release

This section describes updates and important information related to the component delivered in this version. This release also includes enhancements and fixes provided in previous versions. See [Previous Releases](#).

Feature Enhancements

This section describes feature enhancements for this release.

Defaults on Advanced Pane

In the configuration of a Tenable.sc or Tenable.io server, the following default values have changed on the Add Tenable Server, Advanced pane:

- **Maximum number of seconds a request is in queue:** Increased from 10 seconds to 600 seconds
- **Number of queued requests to trigger a scan job:** Increased from 10 to 100
- **Maximum number of scan requests per scan job:** Increased from 50 to 100

Sub-Rule Changes to Basic Tenable Scan Trigger Policy

In the Basic Tenable Scan Trigger policy, there were changes to two sub-rules: the second (Verify time since host last scan) and the fourth (Request a host scan).

In the second sub-rule:

- The default interval between scans changed from 24 hours to 30 days.
- The condition, Last Scan Initiation: Older than 1 days, changed to Last Scan Completed: NOT Older than 30 days.

In the fourth sub-rule:

- The action, Start Tenable Scan, is no longer selected by default. You must select the checkbox to enable it.

New Authentication for Tenable.io

A new authentication, API Key/Secret, has been added for Tenable.io.

When configuring the eyeExtend module to communicate with a Tenable.io server using *API Key/Secret* authentication, enter the API access key and secret key on the Add Tenable Server, General pane. On this pane, the **Validate Server Certificate** checkbox is selected by default. It is strongly recommended to keep the checkbox selected to verify the Tenable.io server.

Tenable Property Removed from Discovery

The property, *Tenable Scan Results*, has been removed from Options > Discovery > Inventory.

The warning in the Asset Inventory when you select *Tenable Scan Results* has been shortened. It used to read: Note that data in this view is collected from endpoints based only on policies. Adding this property to the Inventory Discovery may impact network traffic. Do you want to add the Tenable Scan Results property to the Inventory Discovery? **Yes/No**

Now it reads: Note that the data in this view is collected from endpoints based only on policies. **OK**

Fixed Issues

This section describes the fixed issues for this version of Forescout eyeExtend for Tenable VM.

Defect #	Description
TVM-1001	Reduced the number of API calls made to the Tenable.io cloud when a scan is submitted.

Known Issues

This section describes the known issues for this version of Forescout eyeExtend for Tenable VM.

Defect #	Description
TVM-785	Forescout eyeExtend for Tenable VM needs to be restarted after a Certificate Authority (CA) or self-signed server certificate is installed.
TVM-942	Forescout eyeExtend for Tenable VM does not support Certification Compliance mode. For information about this mode, refer to the <i>Forescout Installation Guide</i> .
TVM-947	<p>The Test button fails the <i>Trigger a test scan</i> test under the following conditions:</p> <ul style="list-style-type: none"> ▪ When the Tenable server is defined with the following values in the General pane: <ul style="list-style-type: none"> - Server Type is Tenable.sc - Use DNS Name (if available) is selected - User Name is part of an organization whose Distribution Method is either Selectable Zones or Locked Zone ▪ And when the Test Parameters pane has the following values: <ul style="list-style-type: none"> - Endpoint has a valid FQDN - Trigger a test scan is selected <p>With this configuration, selecting Test results in the Tenable VM Plugin Configuration Test pane displaying a single line for the <i>Last Scan</i> test, but missing the line for the <i>Trigger a test scan</i>.</p> <p>The workaround is to use an IP address for Endpoint.</p>


How to Install


To install the module:

1. Navigate to one of the following Forescout download portals, depending on the licensing mode your deployment is using:
 - [Product Updates Portal](#) - **Per-Appliance Licensing Mode**
 - [Customer Portal, Downloads Page](#) - **Flexx Licensing Mode**

To identify your licensing mode, select **Help > About ForeScout** from the Console.

2. Download the module `.fpi` file.
3. Save the file to the machine where the Console is installed.
4. Log into the Console and select **Options** from the **Tools** menu.
5. Select **Modules**. The Modules pane opens.
6. Select **Install**. The Open dialog box opens.
7. Browse to and select the saved module `.fpi` file.
8. Select **Install**. The Installation screen opens.
9. Select **I agree to the License Agreement** to confirm that you have read and agree to the terms of the License Agreement and select **Install**. The installation cannot proceed unless you agree to the license agreement.

 *The installation begins immediately after selecting Install and cannot be interrupted or canceled.*

 *In modules that contain more than one component, the installation proceeds automatically one component at a time.*

10. When the installation completes, select **Close** to close the window. The installed module is displayed in the Modules pane.

 *Some components are not automatically started following installation.*

More Release Information

This section provides additional release information.

Rollback Support

Rollback is not available for this module. This means that if you upgrade to this module version and the module does not operate as expected, you cannot roll it back to a previous release.

Previous Releases

Installing this release also installs fixes and enhancements provided in the releases listed in this section. To view Release Notes of previous version releases, see:

<https://www.forescout.com/company/resources/eyeextend-for-tenable-vulnerability-management-release-notes-3-0-1/>

<https://www.forescout.com/company/resources/eyeextend-for-tenable-vulnerability-management-release-notes-3-0-0/>

<https://www.forescout.com/company/resources/eyeextend-for-tenable-vulnerability-management-release-notes-2-9-0/>

<https://www.forescout.com/company/resources/eyeextend-for-tenable-vulnerability-management-release-notes-2-8-1/>

<https://www.forescout.com/company/resources/eyeextend-for-tenable-vulnerability-management-2-8-release-notes/>

Contact Information

Forescout Technologies, Inc.

190 West Tasman Drive

San Jose, CA 95134 USA

<https://www.Forescout.com/support/>

Toll-Free (US): 1.866.377.8771

Tel (Intl): 1.408.213.3191

Support: 1.708.237.6591

About the Documentation

- Refer to the Technical Documentation page on the Forescout website for additional documentation: <https://www.Forescout.com/company/technical-documentation/>
- Have feedback or questions? Write to us at documentation@forescout.com

Legal Notice

© 2020 Forescout Technologies, Inc. All rights reserved. Forescout Technologies, Inc. is a Delaware corporation. A list of our trademarks and patents can be found at <https://www.Forescout.com/company/legal/intellectual-property-patents-trademarks>. Other brands, products, or service names may be trademarks or service marks of their respective owners.