

# Forescout

# Asset Reporting Format (ARF) Reports Module

**Configuration Guide** 

Version 1.0.3



### **Contact Information**

Forescout Technologies, Inc. 190 West Tasman Drive San Jose, CA 95134 USA https://www.forescout.com/support/ Toll-Free (US): 1.866.377.8771 Tel (Intl): 1.408.213.3191 Support: 1.708.237.6591

### About the Documentation

- Refer to the Resources page on the Forescout website for additional technical documentation: <u>https://www.forescout.com/company/resources/</u>
- Have feedback or questions? Write to us at <u>documentation@forescout.com</u>

### Legal Notice

© 2019 Forescout Technologies, Inc. All rights reserved. Forescout Technologies, Inc. is a Delaware corporation. A list of our trademarks and patents can be found at <u>https://www.forescout.com/company/legal/intellectual-property-patents-trademarks</u>. Other brands, products, or service names may be trademarks or service marks of their respective owners.

2019-02-28 17:00

# **Table of Contents**

About the ARF Reports Module 4	
Report Content4	
Assets4	
Reports5	
Report File Transfer	
Requirements5	
Install the Module	
Configure the Module	
Verify That the Module Is Running6	
Working with the ARF Report Template7	
Immediate Report Generation7	
Scheduled Report Generation8	
Creating an ARF Report8	
Additional Forescout Documentation 11	
Documentation Downloads11	
Documentation Portal12	
Forescout Help Tools12	

### **About the ARF Reports Module**

The Forescout<sup>®</sup> ARF Reports Module provides CounterACT users with the **ARF Report** template, which is available in the Forescout **Reports Portal**. Working with this report template, users define and generate reports that provide information about assets detected by the Forescout platform.

The structure and content of these reports follow the Asset Reporting Format (ARF) data model, which is a component of the Security Content Automation Protocol (SCAP). ARF is a standard for compiling IT asset information. Information that is compiled using this standard can be easily shared with third-party systems.

ARF Reports are generated in XML format into a file that is then transferred to a remote server, which is specified by the user.

All features provided by the Forescout **Reports Portal** are available for use with the **ARF Report** template. These include accessing reports, scheduling reports, saving reports and managing reports. For feature information available with the **Reports Portal**, refer to the *Forescout Core Extensions Module: Reports Plugin Configuration Guide*.

### **Report Content**

ARF reports contain the following XML sections:

- <u>Assets</u>
- <u>Reports</u>

### Assets

The XML section **assets** provides the **computing-device** properties for each detected asset. The report lists each detected asset by an assigned **asset-id**. Properties reported per asset are:

- Common Platform Enumeration (CPE): IT product and platform information encoded in a standard, machine-readable format. CPE information is reported for Windows, Macintosh and Linux endpoints.
  - For the Module to report operating system CPE information, these endpoints must be managed by Remote Inspection or by the SecureConnector. The ARF Reports Module obtains operating system CPE information about these endpoints from the resolved OS CPE Format property.

CPE information examples:

- Windows: cpe:2.3:o:microsoft:Windows\_Server\_2008\_64-bit\_R2:-:Service\_Pack\_1:-:\*:Enterprise\_Edition
- Macintosh: cpe:2.3:o:apple:mac\_os\_x:10.8.0:\*:\*:\*:\*:\*:\*:\*
- Linux: cpe:2.3:o:centos:centos:6.1:\*:\*:\*:\*:\*:\*
- Connections:
  - IP address

- MAC address
- Fully Qualified Domain Name (FQDN)
- Host Name

When no information is available to report about a property, that property is not listed for the detected asset. For example, if a detected asset has no FQDN, there will be no **fqdn** entry for the asset listed in the report.

### Reports

The XML *reports* section appears following the XML *assets* section. The Module does not provide any information in this section. This section can be ignored.

### **Report File Transfer**

Definition of an **ARF Report** template includes a remote server location to where the generated report is transferred (a server location that should be accessible to report consumers). The following data transfer protocols are available:

- FTP
- SFTP
- SCP

Example:

Define an ARF report that is generated daily at 5:00 am and transferred via SFTP to your Enterprise GRC system.

# Requirements

The Module requires the following components:

- Forescout 8.1.
- Core Extensions Module version 1.1 with the Reports Plugin running.
- If you want the ARF Reports Module to provide CPE information about Windows endpoints, install Windows Applications version 2.1.4.
- If you want ARF Reports Module to provide CPE information about Macintosh and Linux endpoints, you must have Endpoint Module version 1.1 with the following components running:
  - Linux Plugin, if there are Linux endpoints in your environment
  - OS X Plugin, if there are macOS/OS X endpoints in your environment

### Install the Module

#### To install the module:

- 1. Navigate to one of the following Forescout download portals, depending on the licensing mode your deployment is using:
  - Product Updates Portal Per-Appliance Licensing Mode
  - <u>Customer Portal</u>, <u>Downloads Page</u> *Flexx Licensing Mode*

To identify your licensing mode, select **Help > About Forescout** from the Console.

- 2. Download the module .fpi file.
- 3. Save the file to the machine where the Console is installed.
- 4. Log into the Console and select **Options** from the **Tools** menu.
- 5. Select Modules. The Modules pane opens.
- 6. Select Install. The Open dialog box opens.
- 7. Browse to and select the saved module .fpi file.
- 8. Select Install. The Installation screen opens.
- **9.** Select **I agree to the License Agreement** to confirm that you have read and agree to the terms of the License Agreement, and select **Install**. The installation will not proceed if you do not agree to the license agreement.
  - The installation will begin immediately after selecting Install, and cannot be interrupted or canceled.
  - In modules that contain more than one component, the installation proceeds automatically one component at a time.
- **10.**When the installation completes, select **Close** to close the window. The installed module is displayed in the Modules pane.
  - Some components are not automatically started following installation.

# **Configure the Module**

This Module does not require any configuration.

### Verify That the Module Is Running

After configuring the module, verify that it is running.

#### To verify:

- 1. Select Tools>Options and then select Modules.
- 2. Navigate to the module and select Start if the module is not running.

# Working with the ARF Report Template

Use the **ARF Report** template to define reports that provide property information about detected assets. Module generated ARF reports are in XML format. As with other Forescout 8.1 reports, an ARF report can be either immediately generated or generated on a scheduled basis.

### **Immediate Report Generation**

With immediate report generation, the following occurs:

 The generated report is transferred in a file to a remote server location, based on the information you defined in the report template parameters page. The file name format is

```
arf_report_template_Forescout_report_<Day_Month_Date>_<HH_MM_SS>_
<Time Zone>_<Year>-<count>.xml.
```

Where:

- <HH\_MM\_SS> is in 24 hour format.
- <count> is an integer value, starting at zero, that is incremented with each, subsequent, generated report. <count> resets to zero every time the Enterprise Manager is restarted.

File name example:

arf\_report\_template\_Forescout\_report\_Tue\_Jun\_10\_19\_55\_38\_CDT\_20148.xml.

• The generated report is displayed in a web page, using your machine's default web browser. For the list of supported browsers, refer to the *Forescout Core Extensions Module: Reports Plugin Configuration Guide*.



### **Scheduled Report Generation**

With scheduled ARF Report generation, the following occurs:

• The generated report is transferred in a file to a remote server location, based on the file transfer information you defined in the report template parameters page. The file name format is

arf\_report\_template\_Forescout\_report\_<Day\_Month\_Date>\_<HH\_MM\_SS>\_
<Time Zone>\_<Year>-<count>.xml. For details about the file name format, see
Immediate Report Generation.

• The generated report is delivered by email to the email address you defined in the report template parameters page. It is sent in an attached file that has the same file name as the transferred file.

### **Creating an ARF Report**

#### To create an ARF Report:

1. Select the **Ellipsis icon** from the **Toolbar** menu and select **Reports** from the dropdown menu. The Reports page opens in a browser.



2. In the Reports page, select Add. The Add Report Template dialog opens.



**3.** Select **ARF Report** and then select **Next**. The report template parameters page opens.

Amere         Marrie         Marrie         Secretation:         Image:         Secretation:         Secretatio:         Secretation:			
NeF Root Evangle   secretad by:	1. Header		
Beeription: <ul> <li></li></ul>	Name:		
Apper Floot:         Separe Floot:	ARF Report Example		
Apport Foder:   Secreted by:   Secreted by: <td>Description:</td> <td></td> <td></td>	Description:		
Apport Foder:   Secreted by:   Secreted by: <td>2 2</td> <td></td> <td></td>	2 2		
admin       2. Scope         Prace:	Report Footer:		
admin       2. Scope         Prace:			
2. Scope           Prages:	Generated by:		
Prage:	admin		
Prage:	2. Scope		
• All Ps         • Range       - To-         • Segment () summary in tooling i         • Segment () summary in tooling i         • Variance         • Variance         • Range         • Range         • Range         • Range         • Variance         • Variance         • Packatan Server         • Packatan Server <td></td> <td></td> <td></td>			
A Target           Ille transfer parameters :           Protecto Intramifer lie C r pr C strp C	C Range -To - C Segment Editi≫	Segment(s) summary in tooltp	
Potocol to Transfer Re C prp C scp         Destination Server         Pot         Pot         Destination Server         Pot         Pot         Destination Server         Poto         Poto         Poso         C banky         Sendel Ber port         C banky         2 Doubling Report         Sendel Report	3. Target		
Bestantion Server	File transfer parameters :		
Schedule the report:           Ø None           C Daby At         12:00 AM IM           C Daby At         12:00 AM IM           Send Report to	Port Username Password Reenter Password Directory to Receive File		
None           C Daly At         12 00 AM I           C Every         Monday         At           Send Report to:	4. Schedule		
C Daily At         12:00 AM Image: Amage: Amage	Schedule the report:		
de Back	C Daily At 12:00 AM		
	Jack Back		📳 Save 🔰 Run

- 4. In the **Header** section:
  - In the Name field, enter a report name (*required*). Maximum length is 60 characters. The following characters cannot be used in this field:

& # : / ' ` "

- In the **Description** field, enter descriptive text (*optional*).
- In the Generated by field, enter the name of the CounterACT user generating or associated with the report (*optional*). Maximum length is 60 characters.

When an ARF report is generated, the information defined in the **Header** section is not included in the report, since this information is not part of the ARF data model standard. The sole purpose of the information provided in these fields is to support the user of the ARF Report template.

- 5. In the Scope section, select either all IPs, a host IP range or the network IP segments for which to create the report. Select Unknown IP addresses to include hosts at which a MAC address was detected, rather than an IP address.
- 6. In the **Target** section, provide the following details that are used to transfer the generated ARF report to a remote server:
  - **Protocol to Transfer File**: Select the protocol that will be used to transfer the file containing the generated ARF report.
  - Destination Server: Specify the server to which the file will be transferred. Enter either the server IP address, the server FQDN or the server name.
  - Port: Specify the port number to connect to on the remote server. The default port of the selected transfer protocol automatically appears in this field.
  - **User**: Specify the username to use when logging in to the remote server.
  - **Password**: Specify the password to use when logging in to the remote server.
  - Re-enter Password: Verify the specified password by re-entering it in this field.
  - **Directory to Receive File**: Specify the directory to receive the transferred file.
- 7. In the **Target** section, select **Test File Transfer** to execute a file transfer test based on the information defined in this section.
- 8. In the Schedule section, define a report generation schedule (optional).
  - Define a schedule to generate either
    - a daily recurring report (**Daily At** < *time of day*>)

or a day of week recurring report (**Every** < *day* of week> **At** < *time* of *day*>).

- In the Send Report to field, enter an email address to send the generated report to. You may enter multiple email addresses, separating them with commas.
- **9.** Perform either of the following:
  - Select **Run** to generate a report using the defined report template.
  - Select **Save** to save the defined report template for later use.
  - The defined report template is saved and appears in the **My Reports** table on the **Reports Portal** page.

							Administrator	
							Administrator	
Add	🖌 E	Edit 🛯 🌚 Duplicate 🏢 Remove	Scope Schedule Email O Run				Search	0
•	0	Name *	Description	Scope 0	Format 0	Email 0	Schedule	i
-	1	ARF Report Example 1	CounterACT-detected assets/properties.	All IPs	th:	admin@yourcompany.org	Daily At 11:30 AM	
-	-	Compliance Status1	Show the compliance status of selected hosts.	0.0.0.0-223.255.255.255	1		None	۲

# **Additional Forescout Documentation**

For information about other Forescout features and modules, refer to the following resources:

- <u>Documentation Downloads</u>
- <u>Documentation Portal</u>
- Forescout Help Tools

### **Documentation Downloads**

Documentation downloads can be accessed from the <u>Forescout Resources Page</u>, or one of two Forescout portals, depending on which licensing mode your deployment is using.

- Per-Appliance Licensing Mode Product Updates Portal
- Flexx Licensing Mode <u>Customer Portal</u>
- Software downloads are also available from these portals.

#### To identify your licensing mode:

• From the Console, select **Help > About Forescout**.

#### Forescout Resources Page

The Forescout Resources Page provides links to the full range of technical documentation.

#### To access the Forescout Resources Page:

 Go to <u>https://www.Forescout.com/company/resources/</u>, select Technical Documentation and search for documents.

#### Product Updates Portal

The Product Updates Portal provides links to Forescout version releases, Base and Content Modules, and eyeExtend products, as well as related documentation. The portal also provides a variety of additional documentation.

#### To access the Product Updates Portal:

 Go to <u>https://updates.forescout.com/support/index.php?url=counteract</u> and select the version you want to discover.

#### Customer Portal

The Downloads page on the Forescout Customer Portal provides links to purchased Forescout version releases, Base and Content Modules, and eyeExtend products, as well as related documentation. Software and related documentation will only appear on the Downloads page if you have a license entitlement for the software.

#### To access documentation on the Forescout Customer Portal:

• Go to <a href="https://Forescout.force.com/support/">https://Forescout.force.com/support/</a> and select **Downloads**.

### **Documentation Portal**

The Forescout Documentation Portal is a searchable, web-based library containing information about Forescout tools, features, functionality, and integrations.

If your deployment is using Flexx Licensing Mode, you may not have received credentials to access this portal.

#### To access the Documentation Portal:

 Go to <u>https://updates.forescout.com/support/files/counteract/docs\_portal/</u> and use your customer support credentials to log in.

### **Forescout Help Tools**

Access information directly from the Console.

#### **Console Help Buttons**

Use context sensitive *Help* buttons to quickly access information about the tasks and topics you are working with.

#### Forescout Administration Guide

• Select Forescout Help from the Help menu.

#### **Plugin Help Files**

 After the plugin is installed, select Tools > Options > Modules, select the plugin and then select Help.

#### **Online Documentation**

 Select Online Documentation from the Help menu to access either the <u>Forescout Resources Page</u> (Flexx licensing) or the <u>Documentation Portal</u> (Per-Appliance licensing).